TABLE 1. Command Packet to Handler Object Map

Command	Opcode Symbol	Object Name	Class Name
Load Timed Exposure Parameter Block	CMDOP_LOAD_TE	chLoadTimedExp	ChLoadBlk
Load Cont. Clocking Parameter Block	CMDOP_LOAD_CC	chLoadContClock	ChLoadBlk
Load 2-D Window List	CMDOP_LOAD_2D	chLoad2dWindow	ChLoadBlk
Load 1-D Window List	CMDOP_LOAD_1D	chLoad1dWindow	ChLoadBlk
Load DEA House.Parameter Block	CMDOP_LOAD_DEA	chLoadDeaHouse	ChLoadBlk
Read BEP Memory	CMDOP_READ_BEP	chReadBep	ChReadBep
Write BEP Memory	CMDOP_WRITE_BEP	chWriteBep	ChWriteBep
Execute BEP Memory	CMDOP_EXEC_BEP	chExecBep	ChExecBep
Read FEP Memory	CMDOP_READ_FEP	chReadFep	ChReadFep
Write FEP Memory	CMDOP_WRITE_FEP	chWriteFep	ChWriteFep
Execute FEP Memory	CMDOP_EXEC_FEP	chExecFep	ChExecFep
Read PRAM	CMDOP_READ_PRAM	chReadPram	ChReadPram
Write PRAM	CMDOP_WRITE_PRAM	chWritePram	ChWritePram
Read SRAM	CMDOP_READ_SRAM	chReadSram	ChReadSram
Write SRAM	CMDOP_WRITE_SRAM	chWriteSram	ChWriteSram
Start Timed Exposure	CMDOP_START_TE	chStartTimedExp	ChStartSciRun
Start Timed Exposure Bias Only	CMDOP_BIAS_TE	chBiasTimedExp	ChStartSciRun
Stop Timed Exposure	CMDOP_STOP_TE	chStopTimedExp	ChStopSciRun
Start Continuous Clocking	CMDOP_START_CC	chStartCc	ChStartSciRun
Start Continuous Clocking Bias Only	CMDOP_BIAS_CC	chBiasCc	ChStartSciRun
Stop Continuous Clocking	CMDOP_STOP_CC	chStopCc	ChStopSciRun
Start DEA Housekeeping	CMDOP_START_DEA	chStartDeaRun	ChStartDeaRun
Stop DEA Housekeeping	CMDOP_STOP_DEA	chStopDeaRun	ChStopDeaRun
Add Patch	CMDOP_ADD_PATCH	chAddPatch	ChAddPatch
Remove Patch	CMDOP_REMOVE_PATCH	chRemovePatch	ChRemovePatch
Add Bad Pixel	CMDOP_ADD_BAD_PIXEL	chAddBadPixel	ChAddBadPixel
Remove Bad Pixel	CMDOP_REMOVE_BAD_PIXEL	chRemoveBadPixel	ChRemoveBadPixel
Dump Bad Pixels	CMDOP_DUMP_BAD_PIXELS	chDumpBadPixels	ChDumpBadPixels
Add Bad Timed Exposure Column	CMDOP_ADD_BAD_TE_COL	chAddBadTeCol	ChAddBadCol
Remove Bad Timed Exposure Column	CMDOP_REMOVE_BAD_TE_COL	chRemoveBadTeCol	ChRemoveBadCol
Dump Bad Timed Exposure Columns	CMDOP_DUMP_BAD_TE_COL	chDumpBadTeCol	ChDumpBadCol
Add Bad Continuous Clocking Column	CMDOP_ADD_BAD_CC_COL	chAddBadCcCol	ChAddBadCol
Remove Bad Cont. Clocking Column	CMDOP_REMOVE_BAD_CC_COL	chRemoveBadCcCol	ChRemoveBadCol
Dump Bad Cont. Clocking Columns	CMDOP_DUMP_BAD_CC_COL	chDumpBadCcCol	ChDumpBadCol
Change System Configuration Entry	CMDOP_CHANGE_SYS_ENTRY	chChangeSysEntry	ChChangeSysEntry
Dump System Configuration Entries	CMDOP_DUMP_SYS_CONFIG	chDumpSysConfig	ChDumpSysConfig